



SEAN SHEEP^{Baaa!}

Cable Throw

Yarn required:

SEAN SHEEP ROKEWOOD

Three Colour Throw

8 x 50g balls 1st Colour (C1)

8 x 50g balls 2nd Colour (C2)

8 x 50g balls 3rd Colour (C3)

Single Colour Throw

24 x 50g balls



More free
patterns available
for download at
www.seansheep.com

Skill Level
Intermediate

Cable Throw

(Intermediate)

MEASUREMENTS

Width (approx) 100 cms/40 ins

Length (approx, excluding tassels)

100 cms/40 ins

SEAN SHEEP YARN ROKEWOOD

Three Colour Throw

4 x 100g balls 1st Colour (**C1**)

4 x 100g balls 2nd Colour (**C2**)

4x 100g balls 3rd Colour (**C3**)

Single Colour Throw

12 x 100g balls

NEEDLES

A pair 10.00mm (US 15), (UK 000) Knitting Needles **or size that gives correct tension/gauge.**

MATERIALS

A Cable Needle; A Yarn Needle.

TENSION/GAUGE

8.5 sts and 12 rows to 10 cm/4 ins over stocking st, using 10.00mm (US 15), (UK 000) Knitting Needles and 2 strands of yarn together.

Note - Correct tension/gauge is essential for a successful handknit.

ABBREVIATIONS

St/s - stitch/es, **K** - Knit, **P** - purl, **garter st** - every row knit, **stocking st** - 1 row K, 1 row P, **RS** - right side, **WS** - wrong side, **inc** - increase, **beg** - begin/ning, **patt** - pattern, **rep** - repeat, **cont** - continue, **P2tog** - purl 2 sts together.

SPECIAL ABBREVIATION

C12B - slip next 6 sts onto cable needle and leave at back of work, K6, then K6 from cable needle.

CREATE

Three Colour Throw (worked in panels)

Panel A (make 2)

Using 10.00mm (US 15), (UK 000) Needles and 2 strands of **C1** together, cast on 16 sts. Knit 2 rows garter st (1st row is WS).

3rd row - K4, P2, inc purlways once in each of next 4 sts, P2, K4 = 20 sts.

Beg patt - 1st row (RS) - K2, P2, K12, P2, K2.

2nd row - K4, P12, K4.

Rep 1st and 2nd rows 3 times.

9th row - K2, P2, **C12B**, P2, K2.

10th row - As 2nd row.

Rep 1st and 2nd rows 4 times.

Last 18 rows form patt.

Cont in patt until work measures approx 98 cms/39 ins from beg, ending with a 15th patt row.

Next row (WS) - K4, P2, (P2tog) 4 times, P2, K4 = 16 sts.

Knit 2 rows garter st.

Cast/bind off loosely knitways.

Panel B (make 2)

Work as for Panel A, using 2 strands of **C3** together in place of C1.

Panel C (make 1)

Work as for Panel A, using 2 strands of **C2** together in place of C1.

Single Colour Throw

Work to correspond with **Three Colour Throw**, working in one colour only, noting to have 2 strands of yarn together throughout.

FINISHING

DO NOT PRESS. Using yarn needle, darn in ends.

Using yarn needle and a flat seam, sew panels together in following order - Panel A, B, C, A and B.

Make 4 tassels using **C1, C2 and C3**, each tassel being 20 cms/8 ins long when finished. = 12 tassels in total.

Attach tassels evenly along cast on and cast/bound off edges of throw as pictured.